


gcmfaces

a Matlab framework for the
analysis of gridded earth variables



G     Forget *gforget@mit.edu*

Dept. of Earth, Atmospheric and Planetary Sciences
Massachusetts Institute of Technology
Cambridge MA 02139 USA

January 14, 2016

Contents

1	Download And Update	3
1.1	download frozen copies	3
1.2	use the MITgcm CVS server	3
1.3	getting started with gcmfaces	4
2	The gcmfaces class	7
3	Basic Features	10
3.1	Grid Variables	10
3.2	Exchange Functions	12
3.3	Overloaded Functions	12
3.4	I/O Functions	13
4	Tutorial	13
5	Standard Analysis	17

Summary

gcmfaces is a Matlab framework designed to handle gridded earth variables; results of **MITgcm** ocean simulations originally ([Forget et al., 2015](#)). It allows users to seamlessly deal with various gridding approaches (e.g. see Fig.2) using compact and generic codes. It includes many basic and more evolved functionalities such as plotting, or computing transports, gradients, and budgets. **MITprof** is a complementary toolbox to handle in-situ ocean observations ([Forget et al., 2015](#)). This document provides guidelines to download and update the software (section 1) followed by the **gcmfaces** documentation. Its design and basic features are presented in sections 2 and 3. Higher level functions are illustrated in sections 4 and 5.

References

Forget, G., J.-M. Campin, P. Heimbach, C. N. Hill, R. M. Ponte, and C. Wunsch, 2015: ECCO version 4: an integrated framework for non-linear inverse modeling and global ocean state estimation. *Geoscientific Model Development*, **8** (10), 3071–3104, doi:10.5194/gmd-8-3071-2015, URL <http://www.geosci-model-dev.net/8/3071/2015/>.

Disclaimer

The free software programs may be freely distributed, provided that no charge is levied, and that the disclaimer below is always attached to it. The programs are provided as is without any guarantees or warranty. Although the authors have attempted to find and correct any bugs in the free software programs, the authors are not responsible for any damage or losses of any kind caused by the use or misuse of the programs. The authors are under no obligation to provide support, service, corrections, or upgrades to the free software programs.

1 Download And Update

There are two ways to download and start using **gcmfaces** and **MITprof**:

1. download frozen copies: arguably the simplest method that will work in all computing environments (Linux, iOS, MS-windows).
2. use the **MITgcm** CVS server: this is the recommended method under Linux and iOS (assuming CVS was installed) since it has the major advantage that the codes can later easily be updated.

This section documents both methods and the setup of **gcmfaces**.

1.1 download frozen copies

The frozen copies of **gcmfaces** and **MITprof** are stored at

ftp://mit.ecco-group.org/ecco_for_las/version_4/checkpoints/

Download the latest versions¹, uncompress and untar them, and rename the two directories as ‘**gcmfaces**’ and ‘**MITprof**’. When starting Matlab, one will add these two directories to the path as explained in section 1.3.

1.2 use the MITgcm CVS server

Login to the **MITgcm** CVS server as explained in [this page](#) then download the up to date versions of **gcmfaces** and **MITprof** by typing

```
cvs co -P -d gcmfaces MITgcm_contrib/gael/matlab_class
cvs co -P -d MITprof MITgcm_contrib/gael/profilesMatlabProcessing
```

All past and future evolutions of the codes can be traced using the **cvs** version control system. To update an existing copy of the codes and

¹gcmfaces.20160114.tar.gz and c65r-MITprof.tar.gz at the time of writing.

22 take advantage of the latest developments one typically goes inside a di-
23 rectory and types 'cvs update -P -d' at the command line. If you are
24 new to **cvs** then you may want to read about the update command at
25 http://mitgcm.org/public/using_cvs.html.

26 **1.3 getting started with gcmfaces**

27 Download the LLC90 grid (Forget et al., 2015) directory at
28 ftp://mit.ecco-group.org/ecco_for_las/version_4/release1/nctiles_grid/
29 as shown in Fig. 1. Then start Matlab and load the grid by typing:

```
30 %add gcmfaces and MITprof directories to Matlab path:  
31 p = genpath('gcmfaces/'); addpath(p);  
32 p = genpath('MITprof/'); addpath(p);  
33  
34 %load nctiles_grid in memory:  
35 grid_load;  
36  
37 %displays list of grid variables:  
38 gcmfaces_global; disp(mygrid);
```

39 The applications in sections 4 and 5 further require downloading:
40 ftp://mit.ecco-group.org/ecco_for_las/version_4/release1/nctiles_climatology/
41 and adding the **m_map** plotting toolbox to the Matlab path:
42 <https://www.eoas.ubc.ca/rich/map.html>

Figure 1: Directory structure that is consistent with the Matlab commands in Sect. 1.3. The `nctiles_climatology/` directory (14G) contains the monthly mean climatology of the ECCO v4, release 1 state estimate (Forget et al., 2015). `m_map` and `nctiles_climatology/` are not necessary in section 1.3 but are used to demonstrate higher-level functions in sections 4 and 5.

```
./
├── gcmfaces/ (Matlab toolbox)
├── MITprof/ (Matlab toolbox)
├── m_map/ (Matlab toolbox)
├── nctiles_grid/ (netcdf files)
├── release1/
│   ├── nctiles_climatology/ (netcdf files)
│   ├── mat/ (see section 5)
│   └── tex/ (see section 5)
```




Figure 2: Four different ways of gridding the earth. Top left: lat-lon grid, mapping the earth to a single rectangular array ('face'). Top right: cube-sphere grid, mapping the earth to the six faces of a cube. Bottom right: lat-lon-cap 'LLC' grid (five faces). Bottom left: quadripolar grid (four faces). Faces are color-coded, and the ocean topography underlaid. Only a subset of the grid lines are shown in this depiction.

43 2 The gcmfaces class

44 The basic motivation for developing **gcmfaces** was to provide a unified frame-
 45 work that allows for the analysis of earth variables on various grids. Fig. 2
 46 shows four types of grids that are commonly used in ocean general circula-
 47 tion models (GCMs). Despite evident differences in GCM grid designs, such
 48 grids can all be represented as sets of connected arrays (or ‘faces’). This fact
 49 is illustrated in Fig. 3 for the LLC90 grid (bottom right panel in Fig.2) that
 50 is used in ECCO v4 (Forget et al., 2015).

51 The core of **gcmfaces** lies in its definition of a new Matlab data type
 52 (or ‘class’) that represents gridded earth variables as sets of connected ar-
 53 rays (the ‘@gcmfaces/’ subdirectory). An object of the gcmfaces class is
 54 stored in memory as shown in Table 1. The gcmfaces class inherits many
 55 of its basic operations (e.g., ‘+’) from the ‘double’ class as illustrated by
 56 **@gcmfaces/plus.m** (see Table 2). Objects of the gcmfaces class can thus be
 57 manipulated simply through compact and general expressions such as ‘a+b’
 58 (see section 3.3) that are robust to changes in grid design.

Table 1: Gridded variable represented using the gcmfaces class. In this case the LLC90 grid (Fig.2, bottom right) is used that has five faces (f1 to f5).


fld =	
nFaces:	5
f1:	[90x270 double]
f2:	[90x270 double]
f3:	[90x90 double]
f4:	[270x90 double]
f5:	[270x90 double]

Table 2: The '+' operation for gcmfaces objects (@gcmfaces/plus.m).

```
function r = plus(p,q)
%overloaded gcmfaces plus function :
% simply calls double plus function for each face data
% if any of the two arguments is a gcmfaces object

if isa(p,'gcmfaces'); r=p; else; r=q; end;
for iFace=1:r.nFaces;
    iF=num2str(iFace);
    if isa(p,'gcmfaces')&isa(q,'gcmfaces');
        eval(['r.f' iF '=p.f' iF '+q.f' iF ';'']);
    elseif isa(p,'gcmfaces')&isa(q,'double');
        eval(['r.f' iF '=p.f' iF '+q;'']);
    elseif isa(p,'double')&isa(q,'gcmfaces');
        eval(['r.f' iF '=p+q.f' iF ';'']);
    else;
        error('gcmfaces plus: types are incompatible')
    end;
end;
```

Figure 3: Ocean topography displayed face by face for the LLC90 grid (Fig. 2, bottom right). The face indices (from 1 to 5) are overlaid in red. Within each face, grid point indices increase from left to right and bottom to top in this view that reflects the data organization in memory (Tab. 1).



3 Basic Features

The representation of grid variables in memory is documented in section 3.1. Other key features of **gcmfaces** are the ‘exchange’ functions that connect faces (section 3.2) and the ‘overloading’ of common operations (section 3.3). I/O functions are discussed in section 3.4.

3.1 Grid Variables

In practice the **gcmfaces** framework gets activated by loading a grid in memory using the **grid_load.m** function. The default grid (LLC90) can be loaded in memory through a call to **grid_load.m** without any argument (as done in Sect. 1.3). For other grids, **grid_load.m** arguments need to be specified as explained by ‘help grid_load.m’. **grid_load.m** stores all grid variables in memory within a global structure named **mygrid** (Tab.3).

mygrid can be accessed in Matlab at any point by declaring it as ‘global mygrid;’ or using **gcmfaces_global.m**. The latter method additionally: (1) issues a warning when ‘mygrid has not yet been loaded to memory’; provides a few environment variables via **myenv**; adds gcmfaces directories to the path if needed. It should be stressed that gcmfaces functions often rely on **mygrid** and **myenv**. If they get deleted from memory (e.g., by a ‘clear all’) then a call to **grid_load.m** will re-activate gcmfaces properly.

The C-grid variables listed in Tab.3 follow the MITgcm naming convention (see sections 2.11 and 6.2.4 in [this documentation](#)). In brief, XC, YC and RC denote longitude, latitude and vertical position of tracer variables. DXC, DYC, DRC and RAC are the corresponding grid spacings (in m) and grid cell areas (in m²). Another set of such fields (XG, YG, RF, DXG, DYG, DRF, RAZ) is necessary to complete the C-grid specification where velocity variables are shifted compared with tracer variables.

The indexing and vector conventions also derive from the MITgcm. The

Table 3: List of grid variables contained in the mygrid global structure. The naming convention are directly inherited from the MITgcm (see [this online documentation](#)).

XC : [1x1 gcmfaces]	longitude (tracer)
YC : [1x1 gcmfaces]	latitude (tracer)
RC : [50x1 double]	depth (tracer)
XG : [1x1 gcmfaces]	longitude (vorticity)
YG : [1x1 gcmfaces]	latitude (vorticity)
RF : [51x1 double]	depth (velocity along 3rd dim)
DXC : [1x1 gcmfaces]	grid spacing (tracer, 1st dim)
DYC : [1x1 gcmfaces]	grid spacing (tracer, 2nd dim)
DRC : [50x1 double]	grid spacing (tracer, 3rd dim)
RAC : [1x1 gcmfaces]	grid cell area (tracer)
DXG : [1x1 gcmfaces]	grid spacing (vorticity, 1st dim)
DYG : [1x1 gcmfaces]	grid spacing (vorticity, 2nd dim)
DRF : [50x1 double]	grid spacing (velocity, 3rd dim)
RAZ : [1x1 gcmfaces]	grid cell area (vorticity)
AngleCS : [1x1 gcmfaces]	grid orientation (tracer, cosine)
AngleSN : [1x1 gcmfaces]	grid orientation (tracer, cosine)
Depth : [1x1 gcmfaces]	ocean bottom depth (tracer)
hFacC : [1x1 gcmfaces]	partial cell factor (tracer)
hFacS : [1x1 gcmfaces]	partial cell factor (velocity, 2nd dim)
hFacW : [1x1 gcmfaces]	partial cell factor (velocity, 1st dim)

indexing convention is illustrated for the LLC90 grid in Fig. 3. For a vector field the first component (U) points strait to the right of the page in Fig. 3, whereas the second component (V) points strait to the top of the page. The location of U components are shifted by half a grid point towards the left of the page, while the location of V components are shifted by half a grid point towards the bottom of the page (reflecting the C-grid approach).

3.2 Exchange Functions

Many quantities of interests (e.g., budgets) involve values from neighboring grid points that often need to be ‘exchanged’ between faces. This is achieved in practice by appending rows and columns at the sides of each face that are obtained from the neighboring faces – appending rows and columns from faces #2, 3, and 5 at the sides of face #1 in the case of Fig. 3 for example. These exchanges are operated by `exch_T_N.m` for tracer fields and by `exch_UV_N.m` for velocity fields. These functions are needed for example to compute temperature gradients (with `calc_T_grad.m`) and flow convergences (with `calc_UV_conv.m`) as illustrated in section 4.

3.3 Overloaded Functions

Fig. 2 depicts the ‘overloading’ of the ‘+’ operation by `@gcmfaces/plus.m`. In executing commands such as ‘fld+1’, Matlab will use `@gcmfaces/plus.m` if one of the arguments of ‘+’ (i.e. sum) is of the gcmfaces class. Many common operations and functions are similarly overloaded in the ‘@gcmfaces/’ directory that defines the gcmfaces class and its operations:

1. Logical operators: and, eq, ge, gt, isnan, le, lt, ne, not, or
2. Numerical operators: abs, angle, cat, cos, cumsum, diff, exp, imag, log2, max, mean, median, min, minus, mrdivide, mtimes, nanmax,

111 nanmean, nanmedian, nanmin, nanstd, nansum, plus, power, rdivide,
112 real, sin, sqrt, std, sum, tan, times, uminus, uplus.

113 3. Indexing operators: subsasgn, subsref, find, get, set, squeeze, repmat.

114 It is worth mentioning the case of `@gcmfaces/subsasgn.m` (subscripted
115 assignment) and `@gcmfaces/subsref.m` (subscripted reference) since they
116 are some of the most commonly used Matlab functions. For example, if
117 `fld` is of the 'double' class then `'tmp2=fld(1);'` and `'fld(1)=1;'` respectively
118 call `subsref.m` and `subsasgn.m`. If `fld` is of the `gcmfaces` class instead then
119 `@gcmfaces/subsref.m` behaves as follows:

120 `fld{n}` returns the n^{th} face data (i.e. an array).
121 `fld(:, :, n)` returns the n^{th} vertical level (i.e. a `gcmfaces`).

122 And `@gcmfaces/subsasgn.m` behaves similarly but for assignments.

123 3.4 I/O Functions

124 Objects of the `gcmfaces` class can simply be saved to or read from file in
125 Matlab's own I/O format (`.mat` files). The other file formats that are cur-
126 rently supported in the `gcmfaces` framework are: (1) the MITgcm binary
127 formats [documented here](#); (2) the `nctiles` format used to distribute ECCO v4
128 fields ([Forget et al., 2015](#)). When reading from such files, the provided I/O
129 functions (`rdmds2gcmfaces.m` and `read_nctiles.m`, respectively) reformat the
130 input into `gcmfaces` objects on the fly.

131 4 Tutorial

132 Here it is assumed that the user has completed the installation procedure in
133 section [1.3](#) (including the installation of `'nctiles_climatology/'` and `'m_map/'`).

134 `gcmfaces_demo.m` can then be executed that provides examples of a few of
135 the `gcmfaces` capabilities. As prompted by `gcmfaces_demo.m` : specify the
136 desired amount of explanatory text output. `gcmfaces_demo.m`) will then
137 proceed through the examples while displaying explanations in the Matlab
138 command window. The Matlab GUI and debugger can also be used to follow
139 the examples step by step.

140 The first section of `gcmfaces_demo.m` illustrates plotting capabilities.
141 `gcmfaces` relies on `m_map` (<https://www.eoas.ubc.ca/~rich/map.html>) for ge-
142 ographical projections through the `m_map_gcmfaces` front-end that typ-
143 ically produces Fig.4. The `convert2pcol` function provides an alter-
144 native to display results directly via ‘pcolor’ (Fig. 5). The second sec-
145 tion of `gcmfaces_demo.m` focuses on data processing capabilities such
146 as interpolation and smoothing. `example_smooth.m` in particular inte-
147 grates a diffusion equation, which illustrates computations of tracer gradients
148 (`calc_T_grad.m`) and flux convergences (`calc_UV_conv.m`) . The third
149 section of `gcmfaces_demo.m` illustrates computations of oceanic transports
150 and stream-functions (`example_transports.m`).




Figure 4: Same as Fig.3 but plotted in geographical coordinates using `m_map_gcmfaces.m`




Figure 5: Same as Fig.3 but plotted in geographical coordinates using `convert2pcol.m`

151 5 Standard Analysis

152 The gcmfaces standard analysis consists of an extensive set of physical di-
153 agnostics that are routinely monitored in MITgcm simulations and ECCO
154 v4 estimates (Forget et al., 2015). The computational loop is operated by
155 `diags_driver.m` that stores the results in a dedicated directory ('mat/' in
156 Fig.1). The display phase is done afterwards by calling `diags_display.m`
157 (simple display to screen) or `diags_driver_tex.m` (to generate a tex file).

158 Here it is assumed that the user has completed the installation proce-
159 dure in section 1.3 (including the installation of 'nctiles_climatology/' and
160 'm_map/'). The code below then generates mean and variance maps (set-
161 Diags='B' encoded in `diags_set_B.m`) from the ECCO v4 monthly mean
162 climatology (12 monthly fields), which should take about 5 minutes:

```
163 %add paths:
164 p = genpath('gcmfaces/'); addpath(p);
165 p = genpath('MITprof/'); addpath(p);
166 p = genpath('m_map/'); addpath(p);
167
168 %compute diagnostics:
169 help diags_driver;
170 dirModel='release1/';
171 dirMat=[dirModel 'mat/'];
172 setDiags='B';
173 diags_driver(dirModel,dirMat,'climatology',setDiags);
174
175 %display results:
176 diags_display(dirMat,setDiags);
```

177 Each set of diagnostics (computation and display) is encoded in one rou-
178 tine with a name such as 'diags_set_XX.m' (here 'XX' is just a placeholder).
179 These routines can be found in the 'gcmfaces_diags/' directory. Sets of di-
180 agnostics that can be generated using 'nctiles_climatology/' include oceanic
181 transports ('A'), mean and variance maps ('B'), sections and time series ('C'),
182 and mixed layer depths ('MLD').

183 If the 'setDiags' argument to `diags_driver.m` is omitted then the four
184 diagnostic sets will be generated at once, which should takes about 1/2 hour.
185 As this generates a large number of plots, one may prefer to generate a tex
186 file containing all of the plots, which should take another 10 minutes:

```
187 %compute more diagnostics:  
188 dirModel='release1/'; dirMat=[dirModel 'mat/'];  
189 diags_driver(dirModel,dirMat,'climatology');  
190  
191 %generate a tex file containing all of the plots:  
192 dirTex=[dirModel 'tex/']; nameTex='standardAnalysis';  
193 diags_driver_tex(dirMat,{},dirTex,nameTex);
```

194 These diagnostics can also be generated for the full ECCO v4 time series:
195 [ftp://mit.ecco-group.org/ecco_for_las/version_4/release1/nctiles/](http://mit.ecco-group.org/ecco_for_las/version_4/release1/nctiles/)
196 after downloading this directory (243G) and placing it next to 'nctiles_climatology/'
197 in Fig. 1. Since the 20 year time series consists of 240 monthly records, the
198 computation is usually distributed over multiple processors (e.g. each pro-
199 cessor processing one of the years) or done overnight with:

```
200 diags_driver(dirModel,dirMat,[1992:2011]);
```